

How to Make a Nine Patch Baby Quilt

Finished size of baby quilt is 36" x 48"

Main Fabric - 1 yard

White Fabric - 1/2 yard

Accent Fabric #1 - 1/2 yard

Accent Fabric #2 - 1/4 yard

Backing Fabric - 1 3/4 yards

Batting - 42" x 54"

Bias Binding - 5 yard length (2 1/2")

505 Temporary Spray Adhesive

Step 1

Prepare and make 2 1/2" bias binding - Set aside



Step 2



Pick your Accent Fabric by matching the colors printed on the selvage
Wash, dry, and iron all your fabrics



Step 3


Square up the edge of your main fabric
Cut (4) 6 1/2" strips the WOF (width of fabric)
Cut strips into (24) 6 1/2" squares





Step 4

Square up the edge of the white fabric
Cut (7) 2 1/2" strips the WOF



Step 5

Square up the edge of the accent fabric 1
Cut (6) 2 1/2" strips the WOF



Step 6

Sew one accent fabric, one white fabric, and another accent fabric


The white will be down the middle

You will have three sections

Press seams toward the darker fabric

Cut strips into 2 1/2" sections

You should have (48) 2 1/2"




Step 7

Square up the edge of the accent fabric 2
Cut (2) 2 1/2" strips the WOF

Step 8

Sew one white fabric, one accent 2 fabric, and another white fabric
The accent 2 fabric will be down the middle
You will have two sections
Press seams toward the darker fabric
Cut strips into 2 1/2" sections
You should have (24) 2 1/2"



Step 9

Sew the sections together, nesting your seams to form
your 9 patch blocks
Pressing the seams as you go.





Step 10

Lay out your blocks alternating the main fabric and the nine patch blocks
Be mindful if you have a one way design to face them the same way
You will have 6 blocks across and 8 blocks down for a total of 48



Step 11

Place right sides together by placing column 2 on column 1

Chain piece them together.

Repeat with column 4 on column 3

Repeat with column 6 on column 5

Sew all columns together.

Additionally, sew all the rows together.

Your top is done.



Step 12

Lay down your backing with wrong side up

Use spray adhesive and place batting on top of the backing

Use spray adhesive and place top face up on top of the batting



Step 13
Quilt your top as desired
Trim edges even with the top



Step 14


Add bias binding

Lay it out and make sure no seams end up at the corners.



Sew the raw edges of the binding to the edges and finish

Turn to the back and hand stitch binding down



Step 15
Add a label if desired



Step 16
Present your beautiful quilt to the lucky recipient